



1. Open Outlook Express and from "Tools" select "Accounts".



2. Choose "Mail" tab, press "Add" button and then choose "Mail ...".




3. Enter your display name and press "Next".



The screenshot shows a window titled "Internet Connection Wizard" with a close button in the top right corner. The main heading is "Your Name". Below the heading is a mouse cursor icon. The text reads: "When you send e-mail, your name will appear in the From field of the outgoing message. Type your name as you would like it to appear." There is a text input field labeled "Display name:" containing the text "Your Name". Below the field is the example text "For example: John Smith". At the bottom of the window are three buttons: "< Back", "Next >", and "Cancel".

4. Enter your e-mail address and press "Next".



The screenshot shows a window titled "Internet Connection Wizard" with a close button in the top right corner. The main heading is "Internet E-mail Address". Below the heading is a mouse cursor icon. The text reads: "Your e-mail address is the address other people use to send e-mail messages to you." There is a text input field labeled "E-mail address:" containing the text "email@yourdomain.com". Below the field is the example text "For example: someone@microsoft.com". At the bottom of the window are three buttons: "< Back", "Next >", and "Cancel".

5. Enter incoming & outgoing mail server "mail.yourdomain.com" and press "Next".

The screenshot shows the 'Internet Connection Wizard' dialog box with the title bar 'Internet Connection Wizard' and a close button (X) in the top right corner. The main title is 'E-mail Server Names'. Below the title bar, there is a text area with the following content: 'My incoming mail server is a server.' Below this, there is a label 'Incoming mail (POP3, IMAP or HTTP) server:' followed by a text input field containing 'mail.yourdomain.com'. Below that, there is a label 'An SMTP server is the server that is used for your outgoing e-mail.' followed by a label 'Outgoing mail (SMTP) server:' and another text input field containing 'mail.yourdomain.com'. At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'. A mouse cursor is visible in the top right corner of the dialog box.


6. Enter your account password and press "Next".

The screenshot shows the 'Internet Connection Wizard' dialog box with the title bar 'Internet Connection Wizard' and a close button (X) in the top right corner. The main title is 'Internet Mail Logon'. Below the title bar, there is a text area with the following content: 'Type the account name and password your Internet service provider has given you.' Below this, there is a label 'Account name:' followed by a text input field containing 'email@yourdomain.com'. Below that, there is a label 'Password:' followed by a text input field containing seven dots. Below the password field, there is a checked checkbox labeled 'Remember password'. Below this, there is a paragraph: 'If your Internet service provider requires you to use Secure Password Authentication (SPA) to access your mail account, select the "Log On Using Secure Password Authentication (SPA)" check box.' Below the paragraph, there is an unchecked checkbox labeled 'Log on using Secure Password Authentication (SPA)'. At the bottom of the dialog, there are three buttons: '< Back', 'Next >', and 'Cancel'. A mouse cursor is visible in the top right corner of the dialog box.

7. Press "Finish".



8. Choose your e-mail account and Click on "Properties" button.



9. From "Servers" tab check on "My server require authentication" option and press "OK".

The screenshot shows a Windows-style dialog box titled "mail.link.net Properties". It has a blue title bar with a question mark icon and a close button. Below the title bar are five tabs: "General", "Servers", "Connection", "Security", and "Advanced". The "Servers" tab is selected and highlighted in orange. The dialog is divided into three sections: "Server Information", "Incoming Mail Server", and "Outgoing Mail Server".

Server Information

My incoming mail server is a **POP3** server.

Incoming mail (POP3):

Outgoing mail (SMTP):

Incoming Mail Server

Account name:

Password:

Remember password

Log on using Secure Password Authentication

Outgoing Mail Server

My server requires authentication

At the bottom of the dialog are three buttons: "OK", "Cancel", and "Apply".

10. Press "Close" button.

